

Mindwalker 4 Firmware Version 2.01

Release Notes

Issue 1.1 23rd September 2013

V2.01

Previous version introduced a bug which meant that the low battery symbol did not show. This has been corrected.

V2.00

Although the extra features may be of no interest to some, it is recommended that meters are upgraded to the latest firmware to conserve battery power and correct a filter problem – see below.

Filter

Some observant meter users noticed a small 'dip' or 'surge' at the end of a needle motion and this has been corrected. It has been thoroughly tested and the problem resolved to everyone's satisfaction.

Battery Power

Power consumption of the meter has been reduced by 40%. This has been accomplished by turning off the computer USB connection (when not needed).

Body Motion Sensitivity

Some clients with shaky hands or strong heartbeat can trigger the body motion detector. Provision has been made to reduce its sensitivity.

Needle TA Counter

Some users have requested a Needle TA counter – most appropriate for running at low sensitivities where significant counts are missed because the needle does not go off the dial and trigger a SET.

Users should study the revised instructions for the **Set Up Mode** and note that the TA counter mode icon has changed from flashing dots on the right hand display to a triangle on the left display.